


setup iphone english



Welcome to Mail

Cancel New Account Next

Name	Example
Email	example@sx1.net
Password	Kjxd4zzMVM
Description	example@sx1.net

- In Incoming Mail Server
 - Host Name h12.hksx.com
 - User Name (input your own email address)
 - Password (input your own password0)

INCOMING MAIL SERVER

Host Name h12.hksx.com

User Name example@sxl.net

Password Kjxd4zzMVM

- In **Outgoing Mail Server**
 - Host Name h12.hksx.com
 - User Name (input your own email address)
 - Password (input your own password)

OUTGOING MAIL SERVER

Host Name h12.hksx.com

User Name example@sxl.net

Password Kjxd4zzMVM

- tap Save

On existing account

Cancel example@sx1.net Done

Account 

POP ACCOUNT INFORMATION

Name Example

Email example@sx1.net >

Description example@sx1.net

tap the SMTP server name

OUTGOING MAIL SERVER

SMTP h12.hksx.com >

Advanced >

- tap the primary server



- Check Outgoing SMTP settings
 - Use SSL is on
 - Authentication is Password
 - Server Port is 587 (or 465)

Cancel **h12.hksx.com** Done

Server

☒

OUTGOING MAIL SERVER

Host Name

h12.hksx.com

User Name

example@sx1.net

Password

Kjxd4zzMVM

Use SSL

☒

Authentication

Password >

Server Port

587

- Check Incoming POP settings
 - Use SSL is on
 - Authentication is Password
 - Delete from server is Never
 - Server Port is 995

INCOMING MAIL SERVER

Host Name h12.hksx.com

User Name example@sxl.net


Password Kjxd4zzMVM

OUTGOING MAIL SERVER

SMTP h12.hksx.com >


Advanced >

Delete Account




iPhone Always BCC myself and change Signature

- Open Settings > Mail



- Change settings here



From:
<http://wiki.sxl.net/> - wiki

Permanent link:
http://wiki.sxl.net/setup_iphone_english

Last update: **2025/05/11 07:58**

